

Header						Address	Sub-Address	Command	Data Length	Data
0	0	0	0	0	FF	0-FF	0-FF	0-FF	0-FF	

							Data														
Main	Notes	Action	Sub-Address	Command	Command (HEX)	Data Length	Byte:1	2	3	4	5	6	7	8	9	10	11	12			
		NOOP	0	0	0	0															
		Reserve for core protocol	0	1	1	0															
	Starts planned move	Start	0	2	2	0															
		Pause	0	3	3	0															
	Stops planned move. Must be executed before controller will accept other commands.	Stop	0	4	4	0															
	Toggles on/off state of debug LED	Debug LED	0	5	5	0															
		Timing Master	0	6	6	0															
		Set Stored Name	0	7	7	1-10	String [1-10 Characters, Null-terminated, Null padded]														
		Set Device Address	0	8	8	1	2-255														
		Set Common Line for Step Pulsing	0	9	9	1	0,1,2														
		Return Home All Motors	0	10	A	0															
		Motors Max Step Rate	0	11	B	2	Steps/Second [int]														
Not yet implemented	Alt Input Edge (RISING, FALLING, or CHANGE)	0	12	C	1	0,1,2															
Not yet implemented	Alt I/O Mode	0	13	D	2	Ring (0-255)	Tip (0-255)														
	Set Manual Move Flag	0	14	E	1	True/False (1,0)															
	Alt Output Before Shot Delay Time	0	15	F	2	Time (ms) [int]															
	Alt Output After Shot Delay Time	0	16	10	2	Time (ms) [int]															
	Alt Output Before Shot Time	0	17	11	2	Time (ms) [int]															
	Alt Output After Shot Time	0	18	12	2	Time (ms) [int]															
	Alt Output Trigger level	0	19	13	1	HIGH/LOW (1,0)															
	Max Program Run Time	0	20	14	4	Max Run Time (mS) [unsigned long]															
	Start Program Delay	0	21	15	4	Start Time Delay (seconds)															
	Set SMS / Continuous Program Mode	0	22	16	1	0 (SMS), 1 (Cont.)															
		Status Request	0	100			<Status Type>		<returns> with header and master address in front (00 00 00 00 FF 00 00 01 Length Data)												
		Firmware Version	0	100	64	0	[Byte]														
		Run Status	0	101	65	0	[Byte]														
		Run Time	0	102	66	0	[Unsigned Long]														
		Currently Exposing	0	103	67	0	[Byte]														
		Timing Master Value	0	104	68	0	[Byte]														
		Name	0	105	69	0	String [1-10 Characters, Null-terminated, Null padded]														
		Motors Max Step Rate	0	106	6A	0	Steps/Second [int]														
		Voltage Reading	0	107	6B	0	Voltage (V) [Fixed point – must divide by 100 on master side]														
		Current to Motors	0	108	6C	0	Current (amps) [Fixed point – must divide by 100 on master side]														
Not yet implemented	Alt Input Edge (RISING, FALLING, or CHANGE)	0	109	6E	0	0,1,2															
Not yet implemented	Alt I/O Mode	0	110	6F	0	Ring (0-255)	Tip (0-255)														
Not yet implemented	Limit Switch High/Low Status	0	111	70	0	Ring, High/Low (1,0)	Tip, High/Low (1,0)														
	Alt Output Before Shot Delay Time	0	112	70	0	Time (ms) [int]															
	Alt Output After Shot Delay Time	0	113	71	0	Time (ms) [int]															
	Alt Output Before Shot Time	0	114	72	0	Time (ms) [int]															
	Alt Output After Shot Time	0	115	73	0	Time (ms) [int]															
	Alt Output Trigger level	0	116	74	0	HIGH/LOW (1,0)															
	Start Program Delay	0	117	75	0	Start Time Delay (seconds) [long]															
	SMS / Continuous Program Mode	0	118	76	0	0 (SMS), 1 (Cont.)															
	Controller Power Cycle	0	119	77	0	True/False (1,0)															
Motors		NOOP	1-3	0	0	0															
		Reserve for core protocol	1-3	1	1	0															
General Motor Commands	Cuts power to motor when not executing a move. True by default.	Motor Sleep	1-3	2	2	1	True/False (1,0)														
	Must enabled before executing a move.	Motor Enable	1-3	3	3	1	True/False (1,0)														
	Stops motor, even if a planned move is in progress.	Stop Motor Now	1-3	4	4	0															
	Number of steps the motor should move in addition to the commanded distance when reversing direction.	Set Backlash Steps	1-3	5	5	1	Steps [byte]														
	Number of microsteps per full motor step. There are 200 full steps per rotation of the motor (and ~3800 full steps per gearbox output shaft rotation)	Set Microstep Value	1-3	6	6	1	1, 2, 4, 8, 16														
		Set Motor Max Step Speed	1-3	7	7	2	Steps/Second														
	Flips motor direction, regardless of current program	Set Direction	1-3	8	8	1	0, 1														
	Saves home limit position	Set Home Limit Here	1-3	9	9	0															
	Saves end limit position	Set End Limit Here	1-3	10	A	0															
		Send Motor to Home Limit	1-3	11	B	0															
		Send Motor to End Limit	1-3	12	C	0															
Manual Move Commands	Does not apply to finite manual moves	Set Continuous Speed	1-3	13	D	4	Steps/Second [float]														
	Does not apply to finite manual moves	Set Motor Continuous Motion Accel/Decel Rate	1-3	14	E	4	Steps/Second*2 [float]														
	Direct move command, does not require use of "start" and "stop" commands.	Execute Simple Motor Move	1-3	15	F	5	Dir (0, 1)		Steps												

[illegible][illegible][illegible][illegible][illegible][illegible]

		Address	Sub-Address	Command	Data Length	Data
Broadcasts	These function the same as the start, stop, and pause commands above, but can be used to synchronize movement of multiple controllers.	Start	1	0	1	0
		Stop	1	0	2	0
		Pause	1	0	3	0
	Use this to assign an address to a controller with an unknown address. Don't use when controllers are daisy-chained together.	Assign Address	1	0	4	1

Note: nodes do not give a response to broadcast commands.